
## **Date and Time Variable**

To exemplify how you can work with a date and time variable, we are going to build an automation that gets the current date and time, subtracts a specific amount of time and writes the result to a Microsoft Excel spreadsheet.

- 1. Create a new sequence.
- 2. Create two DateTime variables, Today and LastTime.
- Create a TimeSpan variable, called Span, and in the Default field type 1.02:10:04.
  NOTE: The default value attributed to the Span variable uses the day.hh:mm:ss format.
- 4. Add an Assign activity to the **Designer** panel.
- 5. In the Properties panel, in the To field, add the Today variable.
- 6. In the **Value** field, type Now. This gives you the date and time when the project is executed, in the dd/MM/yyyy and hh:mm:ss formats.
- 7. Add another **Assign** activity under the previous one.
- 8. In the Properties panel, in the To field, add the LastTime variable.
- 9. In the Value field, type <code>Today.Subtract(Span)</code>. This is going to subtract the default value of the <code>Span</code> variable from the current date, stored in the <code>Today</code> variable.
- 10. Add an Excel Process Scope activity under the last Assign one. This activity opens or reuses Excel processes, loads the Excel project settings, and applies them to the associated Excel file.
- 11. Add a Use Excel File activity inside the Excel Process Scope activity.
  - **NOTE:** Use the Manage Packages feature to download the Excel activities, if you do not already have them installed.
- 12. In the **Workbook path** field, type the path of the Excel file you want to write to, between quotation marks. In our case, "%HOMEPATH%\Desktop\urgent\_invoice.xlsx".
  - **NOTE:** If the file does not exist at the provided path, it is going to be created.
- 13. Add a Write Cell activity in the Use Excel File activity.
- 14. In the What to write field, type LastTime.ToString. This transforms the value of the LastTime variable to a string and writes it to the coordinates previously given.
- 15. On the right side of the Where to write field, select Plus > Excel > Indicate in Excel.
- 16. Inside the Excel file, indicate the cell in which you want to write (in our case, "E3"). Click **Confirm** after indicating the cell.
  - The final project should look as in the following screenshot:



- 17. Press F5. The automation is executed.
- 18. Navigate to your Excel file and double-click the cell in which you added the date. Note that the time and date information is displayed in the cell you pointed towards.

