

we are going to build the guessing game we did in the previous chapter, the only difference being that we will try to guess a number between 1 and 300.


1. Create a blank process and, on the **Design** tab, in the **File** group, select **New > State Machine**. The **New State Machine** window is displayed.

- Note: You can also add a [State Machine](#) activity to the **Designer** panel to create a new state machine automation.
- In the **Name** field type a name for the automation, such as "First State Machine", and leave the default project location or add a subfolder. Click **Create**. The **Designer** panel is updated accordingly.
- Create two integer variables, `InitialGuess` and `RandomNumber`. The first variable stores your guess, while the second stores the random number.
- Add a **State** activity to the **Designer** panel and connect it to the **Start** node. This is the initial state, and it is used to generate a random number.
- Double-click the activity. This **State** activity is displayed expanded in the **Designer** panel.
- In the **Properties** panel, in the **DisplayName** field, type Initializing Random Number. This enables you to easily tell states apart.
- In the **Entry** section, add an [Assign](#) activity.
- In the **To** field, add the `RandomNumber` variable.
- In the **Value** field, type `new Random().Next(1, 300)`. This expression generates a random number.
- Return to the main project view and add a new **State** activity.
- Connect it to the previously added activity.
- Double-click the last added **State** activity. This activity is displayed expanded in the **Designer** panel.
- In the **Properties** panel, in the **DisplayName** field, type Guess Number. This state is used to prompt the user to guess a number.
- In the **Entry** section, add an [Input Dialog](#) activity.
- Select the **Input Dialog**, and in the **Properties** panel, add an appropriate **Label** and **Title** to prompt the user to guess a number between 1 and 300.
- In the **Result** field, add the `InitialGuess` variable. This variable stores the user's guess.
- Return to the main project view and create a transition that points from the Guess Number state to itself.
- Double-click the transition. The transition is displayed expanded in the **Designer** panel.
- In the **Properties** panel, in the **DisplayName** field, type Try Smaller. This message is displayed on the arrow, enabling you to run through your automation easier.
- In the **Condition** section, type `InitialGuess > RandomNumber`. This verifies if the user's guess is bigger than the random number.
- In the **Action** section, add a [Message Box](#) activity.
- In the **Text** field, type something similar to "Your guess is too big. Try a smaller number." This message is displayed when the user's guess is bigger than the random number.
- Return to the main project view and create a new transition that points from the **Guess Number** state to itself.
- Double-click the transition. The transition is displayed expanded in the **Designer** panel.
- In the **Properties** panel, in the **DisplayName** field, type "Try Bigger". This message is displayed on the arrow, enabling you to run through your automation easier.

- In the **Condition** section, type `InitialGuess < RandomNumber`. This verifies if the guess is smaller than the random number.
- In the **Action** section, add a **Message Box** activity.
- In the **Text** field, type something similar to "Your guess is too small. Try a bigger number." This message is displayed when the users guess is smaller than the random number.
- Return to main project view and add a **Final State** activity to the **Designer** panel.
- Connect a transition from the **Guess Number** activity to the **Final State**.
- In the **Properties** panel, in the **DisplayName** field, type "Correct Guess".
- In the **Condition** field, type `InitialGuess = RandomNumber`. This is the condition on which this automation steps to the final state and end.
- Double-click the **Final State** activity. It is displayed expanded in the **Designer** panel.
- In the **Entry** section, add a **Message Box** activity.
- In the **Text** field, type something similar to "Congratulations. You guessed correctly! The number was " + `RandomNumber.ToString` + "." This is the final message that is to be displayed, when the user correctly guesses the number.


The final project should look as in the following screenshot.

•




- Press F5. The automation is executed correctly.

36.




Load Project as a library:

1. In the **Design** ribbon, select **Export As** and then **Library**.



1. Select the workflows that you want to export as a library. By default, the entire project is deselected, along with the entry points (**Main** workflow, and **Test Cases**).



2. Configure the following **Extract Options**:
 - **Include Test Cases**: By default, this option is enabled for a Process project and disabled for a Test Automation project. You should enable this option if you want to include test cases as part of the extracted library.
 - **Publish and install the library**: Automatically selected to publish the package to a shared feed and install the library as a project dependency. You can disable this option if you want to create the library without publishing it. If disabled, the remainder options are not available for configuration.
 - **Alter your workflows after the package install**: Choose to modify the workflows with activities that have been compiled from the library.
 - **Replacing Mode**: Choose the workflow replacing method.

- Select **Replace invoked workflows content** to change the workflows invoked from entry point, or test cases with corresponding activities from the extracted library.
- Use this option if you use the Isolated and Target Sessions properties for Invoke Workflow activities to run in a separate Windows process, and start in a different session, respectively.
- Select **Replace "Invoke Workflow" activities** to change the [Invoke Workflow](#) activities with activities from the extracted library.

WARNING: Do not select this option if you are using the Isolated and Target Sessions properties for Invoke Workflow activities.

- **Delete replaced workflows:** Delete the workflows that have been replaced by the extracted library activities.
- **Set Execution Templates from library:** Add [execution templates](#) to the library.

3. Click **Export** to confirm the library options.

Export as Library

You can export any process or test automation project as a library to be reused in other projects. We recommend backing up your project or using source control before attempting to export the project to a library as this may change the project structure. [Learn more](#)

Export Options

- ☒ Publish and install the library [?]
- ☒ Alter your workflows after package install [?]
 - ☒ Replace invoked workflows content [?]
 - ☐ Replace "Invoke Workflow" activities [?]
- ☒ Delete replaced workflows [?]
- ☒ Set Execution Templates from library [?]

4. Click **Create** to finish library creation.

Ui

New Blank Library

×

New Blank Library

Create reusable components and publish them together as a library. Libraries ca

Name *

Automation Library


Location *

Description

Library with workflows and test cases


Create

5. (Optional) [Publish the library](#) if you've selected **Publish and install the library** in step 3, and then click **Publish**.



The 'Publish Library' dialog box features a blue title bar with the 'Ui' logo and a close button. On the left, a sidebar contains three tabs: 'Package properties' (selected), 'Publish options', and 'Certificate signing'. The main area is titled 'Package properties' and includes the following fields: 'Package Name *' with a dropdown menu showing 'Automation.Library'; 'Version' section with 'Current Version' (1.0.0) and 'New Version *' (1.0.1) input boxes; an unchecked 'Is Prerelease ?' checkbox; 'Package Icon ?' with a blue icon and a text field containing 'Optional Package Icon' and a file selection button; 'Project tags' with a dropdown menu showing 'Start typing to get a list of possible matches'; and 'Release Notes' with a large empty text area. At the bottom, there are four buttons: 'Cancel', 'Back', 'Next', and 'Publish'.

NOTE: In case you didn't enable the **Publish and install the library** option, you'll be prompted to open the library or continue with the current project.



The 'Extract project success' dialog box has a blue title bar with the 'Ui' logo and a close button. The main area contains a question mark icon in a blue circle followed by the text 'Project BlankLibrary1 created succesfully. Do you want to open it now?'. At the bottom, there are two buttons: 'Yes' and 'No'.

6. Create a new process with this library from the left side menu